

OCTERACT ENGINE

Installation manual



June 25, 2020

Contents

- 1 Overview** **2**

- 2 Installation on Windows** **3**
 - 2.1 Installation 3
 - 2.2 Install a license file manually 5
 - 2.3 Uninstallation 5

- 3 Installation on Linux** **6**
 - 3.1 Installation 6
 - 3.2 Install a license file 6
 - 3.3 Uninstallation 6

Installation manual

Octeract Engine v1.06.10

Copyright (c) Octeract Ltd, 2017-2020

June 25, 2020

1 Overview

Octeract Engine is available for Windows and Linux on 64-bit systems. The rest of the manual assumes you have downloaded the relevant packages for your system (the installer executable for Windows or the tarball for Linux).


2 Installation on Windows

2.1 Installation


Note

In order to install Octeract Engine on your system, you must have administrator rights.


1. Launch octeract-engine-VERSION-setup.exe and click next to start the installation.




2. Accept the terms of the agreement to continue the installation.




3. If you have a license file, you can select it at this step and skip the licensing part of this documentation.




4. Review the details of the components you want to install.



5. Choose the install location of Octeract Engine and click Install to start the installation.



6. That's it! Click Finish to end the installation process.



2.2 Install a license file manually

If you did not install your license through the installation wizard, you can do so manually by moving or copying your license file `OcteractLicense.octeract_lic` to the folder where Octeract Engine is installed. The default location for this is in `C:\ProgramFiles(x86)\Octeract`

2.3 Uninstallation

The usual way of doing this is via the "Programs" section in the "Control Panel". Alternatively, go to folder where Octeract Engine is installed, launch `Uninstall.exe`, and follow the onscreen instructions.

3 Installation on Linux

3.1 Installation

1. Extract the Octeract Engine package (tarball) to a location of your choosing:

```
tar -zxvf octeract.tgz
```

2. Add the `bin` folder to the `$PATH` environment variable and the `lib` folder to the `$PYTHONPATH` environment variable.

3.2 Install a license file

Move or copy your license file `OcteractLicense.otceract.lic` to the folder where Octeract Engine is installed.

3.3 Uninstallation

To uninstall, just delete the folder where Octeract Engine is installed.